


Email Setup for Live Mail 2011

Launch Windows Live Mail

1. Launch Windows Live Mail
2. Select **Accounts** from the top menu bar and then the **Email** icon from the top left



Create new account

3. Enter the **email address** and **password**, then ensure that the **Manually configure server settings** checkbox is ticked

The screenshot shows the 'Add your email accounts' window in Windows Live Mail. The window title is 'Windows Live Mail'. The main heading is 'Add your email accounts' in green. Below it, there is a sub-heading 'If you have a Windows Live ID, sign in now. If not, you can create one later.' and a link 'Sign in to Windows Live'. The form contains several fields and checkboxes:

- Email address:** A text box containing 'you@your-domain.com'. Below it is a link 'Get a Windows Live email address'.
- Password:** A text box with masked characters. Below it is a checked checkbox 'Remember this password'.
- Display name for your sent messages:** A text box containing 'Name Surname'.
- A checked checkbox 'Manually configure server settings'.

On the right side of the form, there is text: 'Most email accounts work with Windows Live Mail including Hotmail Gmail and many others.' At the bottom right, there are two buttons: 'Cancel' and 'Next'.

Configure server settings

4. Select "**POP**" as the Server type and then change your outgoing port number to **587**.
5. Ensure that the **Logon user name** is your entire email address and click "**Next**"

The screenshot shows the 'Configure server settings' dialog box in Windows Live Mail. The window title is 'Windows Live Mail'. The main heading is 'Configure server settings' in green, with a subtitle: 'If you don't know your email server settings, contact your ISP or network administrator.' The dialog is divided into two columns: 'Incoming server information' and 'Outgoing server information'. In the 'Incoming' section, 'Server type' is set to 'POP', 'Server address' is 'mail.your-domain.com', 'Port' is '110', and 'Authenticate using' is 'Clear text'. In the 'Outgoing' section, 'Server address' is 'smtp.your-domain.com', 'Port' is '587', and 'Requires authentication' is checked. There are three buttons at the bottom: 'Cancel', 'Back', and 'Next'.

Windows Live Mail

Configure server settings

If you don't know your email server settings, contact your ISP or network administrator.

Incoming server information

Server type:
POP

Server address: mail.your-domain.com Port: 110

Requires a secure connection (SSL)

Authenticate using:
Clear text

Logon user name:
you@your-domain.com

Outgoing server information

Server address: smtp.your-domain.com Port: 587

Requires a secure connection (SSL)

Requires authentication

Cancel Back Next

Complete Setup

6. Once prompted, you can complete the setup by clicking "**Finish**".



Windows Live Mail



Your email account was added



you@your-domain.com

was added

[Add another email account](#)

Finish